

RDP Gateway Docker Installation

Introduction

Soffid allows you to deploy a new docker container with the **RDP gateway**. The configuration is similar to the sync server configuration.

Prerequisites

The RDP Service is only released as a docker service.

1. Install docker (<https://docs.docker.com/install/>)
2. Install Soffid PAM (store container and launcher container)

You can visit the [PAM Jump Server Installation page](#) for more information about how to install PAM

3. Create a Docker network(*), that network allows you to connect containers to the same bridge network to communicate:

```
sudo docker network create -d bridge NETWORKNAME
```

** You can use the same network defined in the Console and Sync Server installation to avoid visibility problems.*

Installation

The steps required to install RDP container are:

1. Create a user

We need to create a user in the pam store container. To do this, we need to connect to the store container.

```
sudo docker exec -it soffid-pam-store /bin/bash
```

Once, we are connected to the container, we need to run a script to create the user. This script has two parameters, the user name, and the role. We have to type launcher in the role parameter

```
root@soffid-pam-store:/# /opt/soffid/tomee/bin/add-user.sh proxyrdptest launcher
Password: c4ZRcmgemq3nMr1VQJCD1pJRhPbdX5hrmmrP6RX7zBE4HSs3RV3+cGwDdL1WaaqZ
root@soffid-pam-store:/#
```

As a result of the script, we receive the password for the created user. This password will be needed later when we create the container.

2. Create volume

We need to create a volume that will be used by the docker container

```
sudo docker volume create soffid-rdp
```

3. Create a docker container

Finally, we need to execute the command to create the rdp gateway container

```
docker run \
  --name soffid-rdp \
  -e SOFFID_SERVER=https://iam-sync.soffidnet:1760 \
  -e SOFFID_USER=admin \
  -e SOFFID_PASS=changeit \
  -e SOFFID_HOSTNAME=rdp-gateway \
  -e STORE_SERVER=http://soffid-pam-store:8080 \
  -e STORE_PASSWORD=/Dp77Kho5QB2vVKjNNGmXYLzVa6PoPWJ8p0E407EP++9/ZM+I3cieGKMRSgOnFCMc \
  -e STORE_USER=proxyrdp \
  -v soffid-rdp:/opt/soffid/iam-sync/conf \
  --privileged \
  --shm-size=1024m \
```

```
-p 3389:3389 \
--network=soffidnet.intenal \
soffid/pam-rdp:1.4.2
```

Environment Variables

To create the new SSH container you need to set the following environment variables:

| Variable | Description | Example |
|-----------------|---|--------------------------------------|
| SOFFID_SERVER | Sync Server URL | https://syncserver01.soffid.com:1760 |
| SOFFID_USER | Soffid user to join the security domain | admin |
| SOFFID_PASSWORD | Soffid user password | changeit |
| SOFFID_HOSTNAME | The hostname used to access the ssh gateway | ssh-gateway |
| STORE_SERVER | Store URL | http://soffid.pat.pam:8082 |
| STORE_PASSWORD | Password received when you created the user in the store container. | ***** |
| STORE_USER | Store user | proxyrdp |

Revision #11

Created 7 April 2022 09:32:48 by pgarcia@soffid.com

Updated 22 October 2024 14:24:37 by pgarcia@soffid.com