
Authorizations

Definition

Soffid console provides a granular access control system. That granular control system allows the administrator user to assign granular permissions to roles. Be in mind that some permissions may inherit some other permissions.

You cannot assign permissions directly to users. Instead, permissions are assigned to roles and roles are assigned to users, either directly or through grant inheritance.

The roles may be created into Soffid application system, but could also be included in any other application system.

Permissions are grouped into permission scopes. Most scopes are Soffid object types, but there are one special scope named Soffid, that applies to Soffid console web pages.

Addons can create their own authorizations that automatically will appear at this screen. When a new addon has been installed and applied, the first thing to do use to be assign permissions for this new addon. In fact, administrators won't be able to manage the addon unless the log out and log in to get the newly created permissions.

The permissions given to roles and the roles given to users are cached by Soffid. In order to reapply permissions, the user should close its session and log-in again

Screen overview

| ▼ Scope | ▲ ▼ Name | ▲ ▼ Description | ▲ ▼ Roles |
|-----------------|----------------------------|--|-----------|
| Filter | Filter | Filter | Filter |
| Access logs | accessRegister:query | Query all access logs | |
| Accounts | account:update | Update shared accounts | |
| Accounts | account:password | Change shared account password | |
| Accounts | account:create | Create shared accounts | |
| Accounts | account:delete | Delete shared accounts | |
| Accounts | account:query | Query shared accounts | |
| Additional data | metadata:update | Update existing additional data | |
| Additional data | metadata:create | Create new additional data types | |
| Additional data | metadata:delete | Delete a existing additional data type | |
| Additional data | metadata:query | Query the additional data types | |
| Agents | agent:update | Update agents | |
| Agents | agent:create | Create agents | |
| Agents | agent:accessControl:create | Create agents access control rules | |
| Agents | agent:queryObjects | Create target system objects | |
| Agents | agent:delete | Delete agents | |

Related objects

1. **Roles**
2. **Information system**

Standard attributes

- **Scope**: scope of application.
- **Name**: name of the granular permission.
- **Description**: brief description of the granular permission.
- **Roles**: role list assigned to that granular permission.
- **Description**: role description
- **Information system**: asset or application, from a functional point of view.
- **Target system**: target system name.
- **Domain**: the role is limited to that scope.

Actions

Authorization query action

| | |
|--------------------------|--|
| Import | <p>Allows you to upload a CSV file with the authorization data to add or to update the granular control system. If they exist, the values of the CSV file will prevail.</p> <p>First, you need to pick up a CSV file, that CSV has to contain a specific configuration. Then you need to check the contents. And finally, you need to select the mappings for each column of the CSV file to import the data correctly and to click the Import button.</p> |
| Download CSV file | <p>Allows you to download a CSV file with the authorization data.</p> |

Authorization detail actions

| | |
|----------------------|---|
| Add new | <p>Allows you to add a new role to the authorization. You can choose that option clicking the add button (+).</p> <p>First, you need to search a role writing the role name on the field, and Soffid will show the values related. Second, you can select one or more roles and accept.</p> <p>And finally, you need to apply changes to save the roles added. If you cancel that action, no role will be assigned.</p> |
| Delete | <p>Allows you to delete one or more roles from an authorization.</p> <p>To delete one role, you need to click the subtraction symbol (-), located at the end of the row, of the role which you want to delete and then apply changes.</p> <p>To delete more than one role, you can select the roles which you want to delete and there click the subtraction symbol (-) and then apply changes.</p> <p>It is mandatory apply changes to save the roles deleted. Soffid will ask you for confirmation to perform that action, you could confirm or cancel the operation.</p> |
| Apply changes | <p>Allows you to update the changes made on the authorization.</p> |
| Undo | <p>Allows you to quit without applying any changes.</p> |

Revision #11

Created 18 May 2021 12:31:01 by pgarcia@soffid.com

Updated 22 March 2024 08:04:49 by pgarcia@soffid.com