

Hosts

Description

The host screen lets the administrator manage a static IP address assigned to any host. Dynamic IP addresses are automatically managed by Soffid ESSO.

Screen overview

The screenshot displays the Soffid ESSO interface for managing a host. The breadcrumb trail is 'Main Menu > Administration > Resources > Hosts < 6 / 6'. The host configuration is as follows:

Name :	win-604snj52gpc
Description :	Discovered host WIN-6O4SNJ52GPC
Network :	net1 Laboratorio001
DHCP server parameters :	DHCP server parameters
IP Address :	192.168.122.60
Operating system :	Windows Server
Mail server :	<input checked="" type="checkbox"/> No
Shared folders server :	<input checked="" type="checkbox"/> No
MAC Address :	MAC Address
Alias :	Alias
Shared printers server :	<input checked="" type="checkbox"/> No
Dynamic IP :	<input checked="" type="checkbox"/> No
Serial number :	
Last connection :	22/4/2024 12:46
Created on :	22/4/2024 12:46
locked :	<input checked="" type="checkbox"/> No
Device type :	Device type
Operating system :	Operating system
Internet browser :	Internet browser
CPU type :	CPU type

Buttons: Undo, Apply changes

Related objects

1. **Network**
2. **Operating systems**

Custom attributes

Basics

On the basic host tab, you can view all the host attributes. It is allowed to add new host, update or delete existing hosts.

- **Name:** host name.
- **Description:** location, owner and whatever other information you want.
- **Network:** to which it belongs
- **DHCP server parameters:** used by the DHCP agent in order to generate DHCP configuration files.
- **IP Address:** host IP
- **Operating system:** used by the Active Directory agent in order to know if this host must be have an Active Directory host account. Using this functionality, no operator needs to be authorized to add or remove hosts on Active Directory. Soffid will do it for them. More and more, whenever this hosts is left off its IP address, the host account will be removed from Active Directory. This behavior can, of course, be customized.
- **Mail server:** if enabled (selected value is Yes), the user will be able to create mailboxes in the host.
- **Shared folders server:** if enabled (selected value is Yes), the user will be able to create shared folders in the host.
- **MAC Address:** used by the DHCP agent in order to generate DHCP configuration files.
- **Alias:** This field is used to identify the possible IP addresses that may be associated with a single hostname. In complex and segmented environments, it is common for the same machine identifier to be used across multiple networks, whether for service replication, geographic redundancy, or the deployment of parallel test and production environments. This field enables such configurations by linking a hostname to multiple IP addresses, each corresponding to a different network where that hostname is resolvable and operational. As such, the alias acts as an abstraction mechanism that simplifies host identity management in multi-network or multi-site contexts, allowing a single logical identifier (machine name) to be present and active across several network domains, each with its respective IP addressing. The use of the alias field is particularly relevant in distributed architectures, hybrid infrastructures (on-premises and cloud), and high-availability environments, where logical name uniqueness does not imply a single physical address, but rather a flexible, context-dependent association with multiple IP representations of the same functional entity.
- **Shared printer server:** if enabled (selected value is Yes), the user will be able to create a printer queues in the host.
- **Dynamic IP**
- **Serial number**
- **Last connection**
- **Created on**
- **Locked**
- **Device type**
- **Internet browser**

- CPU type

Access Control

On the access control tab, you can delegate the host management.

If you add a user authorization, you will allow the user to execute any task as a local administrator on this server or workstation. **This feature requires the Soffid ESSO** to be installed in the target host. To add a user authorization you can click the button with the add symbol (+), then select the user and expiration date, and finally apply changes.

It is also allowed to delete one or more user authorizations, you can do it from the entitlement details or by selecting one or more records from the list and clicking the button with the subtraction symbol (-).

Additionally, you can download a CSV file with the access control data and you can also upload a CSV file to add user authorizations, and modify or delete user authorizations.

You also can view the administrator password.

Sessions

On the sessions tab, you can view the information about the last connection of a user to this host. Shows data about the user, server, client, port used and date of connection.

You can download a CSV file with the user sessions data.

Actions

Host query

Query	Allows you to query host through different search systems, Quick, Basic and Advanced .
Add or remove columns	Allows you to show and hide columns in the table.
Add new	Allows you to create a new host. You can choose that option on the hamburger menu or by clicking the add button (+). To add a new host it will be mandatory to fill in the required fields

Delete	<p>Allows you to remove one or more hosts by selecting one or more records and next clicking the button with the subtraction symbol (-).</p> <p>To perform that action, Soffid will ask you for confirmation, you could confirm or cancel the operation.</p>
Import	<p>Allows you to upload a CSV file with the host list to add or update hosts to Soffid.</p> <p>First, you need to pick up a CSV file, that CSV has to contain a specific configuration. Then you need to check the content to be loaded, it is allowed to choose if you want or not to load a specific attribute. And finally, you need to select the mappings for each column of the CSV file to import the data correctly and click the Import button.</p>
Download CSV file	<p>Allows you to download a csv file with the hosts information.</p>
Operating systems	<p>This option allows you to manage the Operating Systems. You can add new, update, or delete OS</p>

Host detail

Apply changes	<p>Allows you to save the data of a new host or to update the data of a specific host. To save the data it will be mandatory to fill in the required fields.</p>
Delete	<p>Allows you to delete the host. To delete a host you can click on the hamburger icon and then click the delete button (trash icon).</p> <p>Soffid will ask you for confirmation to perform that action, you could confirm or cancel the operation.</p>
Undo	<p>Allows you to quit without applying any changes.</p>
Assign free IP Address	<p>Allows you to assign a free IP address. You can find that option by clicking on the hamburger icon.</p>
View password	<p>Will show the administrator password if it is available.</p>

Access control

Add new	<p>Allows you to create a new access control. You can choose that option on the hamburger menu or clicking the add button (+).</p> <p>First, you will select the user and the expiration date of that authorization. Finally you need to apply changes.</p>
----------------	---

Delete	<p>Allows you to remove one or more access controls by selecting one or more records and next clicking the button with the subtraction symbol (-).</p> <p>To delete one access control, you can click the access control, and then Soffid will show a form with the details. Then you can click the delete button (trash icon).</p> <p>To perform that action, Soffid will ask you for confirmation, you could confirm or cancel the operation.</p>
Import	<p>Allows you to upload a CSV file with the access control list to add or update access controls to Soffid.</p> <p>First, you need to pick up a CSV file, that CSV has to contain a specific configuration. Then you need to check the content to be loaded, it is allowed to choose if you want or not to load a specific attribute. And finally, you need to select the mappings for each column of the CSV file to import the data correctly and to click the Import button.</p>
Download CSV file	<p>Allows you to download a csv file with the access control information</p>
View password	<p>Will show the administrator password if it is available.</p>

Sessions

Download CSV file	<p>Allows you to download a csv file with the sessions information</p>
--------------------------	--

Revision #24

Created 31 March 2021 08:06:48

Updated 9 June 2025 09:11:48 by Daniel Company