
Printers

Description

Soffid lets administrator users manage system printers. A printer must always be attached to a host. A network attached printer is composed of a host (network print server) and a printer (printer queue).

Printers can be assigned to specific users or to user groups. The effective assignment can be done on session startup by using a Single Sign On client script. To do that, it is necessary to add a script on a Login entry point with type x-mazinger-script.

Related objects

1. **Hosts**
2. **Users**
3. **Groups**

Standard attributes

- **Name:** identifier name of the printer.
- **Description:** additional printer information.
- **Model:** printer model.
- **Server:** where the printer is hosted.
- **Restricted:** if checked, only users and groups of users assigned can be access to that, in another case any user could access to that printer.
- **Users:** assignment of printer queues to users.
- **Groups:** assignment of printer queues to groups

Actions

Printer query

Query	Allows you to query printers through different search systems, Quick , Basic and Advanced .
Add or remove columns	Allows you to show and hide columns in the table.
Add new	Allows you to create a new printer. You can choose that option on the hamburger menu or clicking the add button (+). To add a new printer it will be mandatory to fill in the required fields
Delete	Allows you to remove one or more printers by selecting one or more records and next clicking the button with the subtraction symbol (-). To perform that action, Soffid will ask you for confirmation, you could confirm or cancel the operation.
Import	Allows you to upload a CSV file with the printer list to add or update printers to Soffid. First, you need to pick up a CSV file, that CSV has to contain a specific configuration. Then you need to check the content to be loaded, it is allowed to choose if you want or not to load a specific attribute. And finally, you need to select the mappings for each column of the CSV file to import the data correctly and to click the Import button.
Download CSV file	Allows you to download a csv file with the basic information of all printers.

Printer detail

Add new	Allows you to create a new printer. You can choose that option on the hamburger menu or clicking the add button (+). To add a new printer it will be mandatory to fill in the required fields and apply changes.
Delete	Allows you to remove one printer. You can find that option by clicking on the hamburger icon. To perform that action, Soffid will ask you for confirmation, you could confirm or cancel the operation.
Undo	Allows you to quit without applying any changes.

Revision #18

Created 31 March 2021 08:07:16

Updated 30 November 2022 10:23:51