

How to configure Soffid Authenticator?


Steps to configure Soffid Authenticator

To obtain SSO and MFA for any web or legacy application, you need to configure your Soffid Authenticator App.

1. First of all, you need to login into your Soffid Console and browse **My certificates and FIDO tokens**

Main Menu > My authentication > My certificates and FIDO tokens

2. Second, you must add a new token. You need to click the Add button (+) and select Soffid Authenticator



New token

Select type Finish

Select type : Soffid authenticator

Undo Next

3. Then, you must scan the QR with your device using the Soffid Authenticator App.

New token

Select type


Finish

Please, install the Soffid token app and open this URL or scan the QR code.



← Close

4. To scan this QR code, you must open the Soffid Authentication App on your device



5. Then,

5.1. The first time you open the application, Soffid will ask you about displaying this app over other apps configuration

17:07



soffid

To allow Soffid Authenticator popping up on top of any app, please enable the Display over other apps permissions.

[CANCEL](#) [OPEN SECURITY SETTINGS](#)

AUTHENTICATOR

REGISTER TOKEN

5.1.1. If you select to open security settings, then you must select the authenticator app, and check the Display over other apps option.

a. Select the Special app access option



Special app access

All files access

Device admin apps

No active apps

Display over other apps

Do Not Disturb access

Media management apps

Modify system settings


Device & app notifications

Picture-in-picture


Premium SMS access

Unrestricted data

b. Select the Soffid Authenticator app.



- Check the Allow display over other apps option




5.1.2. If you cancel, the next time you use the app, a notification will be sent to your mobile when an action will be required in the application

5.2. Finally, you must select the Register token option, and register your token



6. Finally, you need to scan the code, and the new token will be registered into Soffid Console.

[Main Menu](#) > [My authentication](#) > My certificates and FIDO tokens ≡

| <input type="checkbox"/> | Type | Serial number | Description | Last use |
|--------------------------|--|-------------------------------------|-------------------------------------|-------------------------------------|
| | | <input type="text" value="Filter"/> | <input type="text" value="Filter"/> | <input type="text" value="Filter"/> |
| <input type="checkbox"/> |  Soffid authenticator | 0000000000036 | Push token 0000000000036 | 04/07/2023 10:22 |

Your Soffid Authenticator is ready to use it.

Revision #9
Created 3 July 2023 11:19:50 by pgarcia@soffid.com
Updated 7 November 2023 10:26:27 by pgarcia@soffid.com