

# Step 2.- How to configure Break glass?

## Configuration

Once you have installed the Break glass addon and Break glass tool, you must configure this tool

## Steps


### Break-glass recovery configuration


1. First of all, you need to configure the Break glass recovery. To do this, you need to browse to Break-glass recovery configuration menu option:


Main Menu > Administration > Configuration > Security settings > Break-glass recovery configuration

2. Then, you need to configure the Authorized users and Authorized application:

### Authorized users

User :   Patricia García

User :   Soffid Administrator

User :   Elizabeth Taylor

Number of users required to break the glass :

### Authorized application

Enabled :

☒ Yes ☐ No

Token :



### Audit information

Created by :	pgarcia	Patricia García
Created on :	24/7/2024 08:22	
Modified by :	pgarcia	Patricia García
Modified last on :	25/7/2024 07:06	

 Undo

 Apply changes

Bear in mind to generate and copy your token because you will need it to configure the Break glass tool

**3.** Click the Apply changes button to save your data.

For more information about this screen, you can visit [the Break-glass recovery configuration page](#).

## Break-glass recovery tool

**4.** Once you have configured your Break-glass recovery configuration, you need to browse to <http://localhost:8445/>

← → ↻ localhost:8445 ☆ jfi fh | Incógnito ⋮

# soffid

Break glass tool

Your break-glass tool is empty. Enter the following parameters to configure it:

Sync server URL:	<input type="text"/>
Authorization token:	<input type="text"/>
Hours between downloads:	<input type="text" value="24"/>
Email to notify errors:	<input type="text"/>
Email to notify when the glass is broken:	<input type="text"/>
Minutes to wait after the glass is broken:	<input type="text" value="10"/>

[Configure](#)

5. Here you need to configure your Break glass tool with the proper data.

Please note that here you need your token, previously copied.

Here is an example:

← → ↻ ⓘ localhost:8445 ☆ .fi .fi | Incógnito

# soffid

Break glass tool

Your break-glass tool is empty. Enter the following parameters to configure it:

Sync server URL:	<input type="text" value="https://sync-server.netcompose:1760/"/>
Authorization token:	<input type="text" value="QRJ"/>
Hours between downloads:	<input type="text" value="24"/>
Email to notify errors:	<input type="text" value="pgarcia@soffid.com"/>
Email to notify when the glass is broken:	<input type="text" value="pgarcia@soffid.com"/>
Minutes to wait after the glass is broken:	<input type="text" value="10"/>

[Configure](#)

6. Click the configure button

6.1. If the data are saved properly this message is displayed:

# soffid

Break glass tool

Your break-glass tool is empty. Enter the following parameters to configure it:

Sync server URL:	<input type="text" value="https://sync-server.netcompose:1760/"/>
Authorization token:	<input type="text" value="QRJ"/>
Hours between downloads:	<input type="text" value="24"/>
Email to notify errors:	<input type="text" value="pgarcia@soffid.com"/>
Email to notify when the glass is broken:	<input type="text" value="pgarcia@soffid.com"/>
Minutes to wait after the glass is broken:	<input type="text" value="10"/>

[Configure](#)

Cannot modify settings

6.2 If the tool can not connect to your Sync Server a message like this will be displayed:

This can be because:

- You need to apply changes at the Break-glass recovery configuration.
- The Authorized application is not enable.
- The token is incorrect.
- The Sync server is down.

soffid

Break glass tool

Your break-glass tool is empty. Enter the following parameters to configure it:

Sync server URL:	<input type="text" value="https://sync-server.netcompose:1760/"/>
Authorization token:	<input type="text" value="QRJIHKReec63G7h7NV-rhVKUQoB9BMUS6MpPST3qdnK"/>
Hours between downloads:	<input type="text" value="24"/>
Email to notify errors:	<input type="text" value="pgarcia@soffid.com"/>
Email to notify when the glass is broken:	<input type="text" value="pgarcia@soffid.com"/>
Minutes to wait after the glass is broken:	<input type="text" value="10"/>

Configure

Cannot connect to https://sync-server.netcompose:1760/

Now the Soffid Breack glass is configured

Revision #8

Created 25 July 2024 06:23:11 by pgarcia@soffid.com

Updated 29 July 2024 13:37:23 by pgarcia@soffid.com