

Step 2.- How to configure Break glass?

Configuration

Once you have installed the Break glass addon and Break glass tool, you must configure this tool

Steps


Break-glass recovery configuration


1. First of all, you need to configure the Break glass recovery. To do this, you need to browse to Break-glass recovery configuration menu option:


Main Menu > Administration > Configuration > Security settings > Break-glass recovery configuration

2. Then, you need to configure the Authorized users and Authorized application:

Authorized users

User :  Patricia García

User :  Soffid Administrator

User :  Elizabeth Taylor

Number of users required to break the glass :

Authorized application

Enabled :

☒ Yes ☐ No

Token :



Audit information

Created by :	pgarcia	Patricia García
Created on :	24/7/2024 08:22	
Modified by :	pgarcia	Patricia García
Modified last on :	25/7/2024 07:06	

[← Undo](#)[✓ Apply changes](#)

Bear in mind to generate and copy your token because you will need it to configure the Break glass tool

3. Click the Apply changes button to save your data.

For more information about this screen, you can visit [the Break-glass recovery configuration page](#).

Break-glass recovery tool

4. Once you have configured your Break-glass recovery configuration, you need to browse to <http://localhost:8445/>

← → ↻ localhost:8445 ☆ jfi fh | Incógnito ⋮

soffid

Break glass tool

Your break-glass tool is empty. Enter the following parameters to configure it:

Sync server URL:	<input type="text"/>
Authorization token:	<input type="text"/>
Hours between downloads:	<input type="text" value="24"/>
Email to notify errors:	<input type="text"/>
Email to notify when the glass is broken:	<input type="text"/>
Minutes to wait after the glass is broken:	<input type="text" value="10"/>

[Configure](#)

5. Here you need to configure your Break glass tool with the proper data.

Please note that here you need your token, previously copied.

Here is an example:

← → ↻ ⓘ localhost:8445 ☆ .fi .fi | Incógnito

soffid

Break glass tool

Your break-glass tool is empty. Enter the following parameters to configure it:

Sync server URL:	<input type="text" value="https://sync-server.netcompose:1760/"/>
Authorization token:	<input type="text" value="QRJ"/>
Hours between downloads:	<input type="text" value="24"/>
Email to notify errors:	<input type="text" value="pgarcia@soffid.com"/>
Email to notify when the glass is broken:	<input type="text" value="pgarcia@soffid.com"/>
Minutes to wait after the glass is broken:	<input type="text" value="10"/>

[Configure](#)

6. Click the configure button

6.1. If the data are saved properly this message is displayed:

soffid

Break glass tool

Your break-glass tool is empty. Enter the following parameters to configure it:

Sync server URL:	<input type="text" value="https://sync-server.netcompose:1760/"/>
Authorization token:	<input type="text" value="QRJ"/>
Hours between downloads:	<input type="text" value="24"/>
Email to notify errors:	<input type="text" value="pgarcia@soffid.com"/>
Email to notify when the glass is broken:	<input type="text" value="pgarcia@soffid.com"/>
Minutes to wait after the glass is broken:	<input type="text" value="10"/>

[Configure](#)

Cannot modify settings

6.2 If the tool can not connect to your Sync Server a message like this will be displayed:

This can be because:

- You need to apply changes at the Break-glass recovery configuration.
- The Authorized application is not enable.
- The token is incorrect.
- The Sync server is down.

soffid

Break glass tool

Your break-glass tool is empty. Enter the following parameters to configure it:

Sync server URL:	<input type="text" value="https://sync-server.netcompose:1760/"/>
Authorization token:	<input type="text" value="QRJIHKReec63G7h7NV-rhVKUQoB9BMUS6MpPST3qdnK"/>
Hours between downloads:	<input type="text" value="24"/>
Email to notify errors:	<input type="text" value="pgarcia@soffid.com"/>
Email to notify when the glass is broken:	<input type="text" value="pgarcia@soffid.com"/>
Minutes to wait after the glass is broken:	<input type="text" value="10"/>

Configure

Cannot connect to https://sync-server.netcompose:1760/

Now the Soffid Breack glass is configured

Revision #8

Created 25 July 2024 06:23:11 by pgarcia@soffid.com

Updated 29 July 2024 13:37:23 by pgarcia@soffid.com