SSH Gateway Connection

Introduction

We can establish a connection to the target system using the SSH remote access protocol.

How to connect 1

You can establish the connection with the ssh gateway and then Soffid will ask your password and the target system parameters to connect:

- Password: password of your account to connect to Soffid.
- Target server: system to which you want to connect.
- Account to use: account to use to connect to the target system.
- Account source system

root@soffid:~# ssh -p 2222 dilbert@ssh-gateway	
Password:	
Target server: 10.129.1	20.5
Account to use: patricia	
Account source system [leave blank to use a target system local account]:	
I _	
/	
/_ _0 _	I
_ / \ /	
_ _/	
_/	
1	
Hello dilbert	
NOTICE: This session is being recorded	
Connecting to 10.129.120.5 as patricia	


Last login: Fri Apr 8 08:39:23 2022 from 10.129.120.6

[patricia@forgecentos ~]\$

How to connect 2

You can establish the connection with the target system typing all the parameters to connect in one line AccountName_HostName_TargetAccount. At the end, Soffid will ask the password of your account to connect.

- Account name: account to connect to Soffid.
- **Host name**: target system to which you want to connect.
- Target account: account to connect to the target system.
- Password: password of your account to connect to Soffid.



How to connect 3

You can establish the connection with the target system typing all the parameters to connect in one line AccountName__HostName__TargetAccount and using a ssh key.

- Account name: account to connect to Soffid.
- **Host name**: target system to which you want to connect.
- Target account: account to connect to the target system.

You can generate an ssh key to connect or use your existing ssh key.

- Generate a new ssh key: ssh-keygen -t rsa
- Read an existing ssh key: cat .ssh/id_rsa.pub

Then you need to include it in Soffid Console in your user data.


Finally you can establish the connection.

Soffid needs the **ssh_key** attribute in the user object metadata, please check the attribute is created properly, and the fill in with your public key.



Q Search

Main Menu > Administration > Configuration > Global Settings > Metadata ◀ 9 / 13 ▶



https://es.wikipedia.org/wiki/Secure_Shell

Revision #18 Created 8 April 2022 08:30:05 Updated 5 December 2024 16:09:18