


Printers

Description

Soffid lets administrator users manage system printers. A printer must always be attached to a host. A network attached printer is composed of a host (network print server) and a printer (printer queue).

Printers can be assigned to specific users or to user groups. The effective assignment can be done on session startup by using a Single Sign On client script. To do that, it is necessary to add a script on a Login entry point with type x-mazinger-script.

Screen overview



The screenshot displays the Soffid web interface for managing Printers. The interface includes a sidebar with navigation options: ISS, IGA, AM, PAM, and IRC. The main content area shows the 'Printers' page with a search bar at the top, a breadcrumb trail 'Main Menu > Resources > Printers', and tabs for 'Quick', 'Basic', and 'Advanced'. Below the tabs are filter buttons for 'Name', 'Description', and 'Model', along with an 'Add criteria' button and a search icon. On the right side, there are buttons for 'Add new', 'Download CSV File', and 'Import'. At the bottom right, there is a 'Search' button with a tooltip that says 'Click search or apply filters'.

Related objects

- **Hosts** : host of the system the requires to have "Shared printers server"=yes.
- **Detected browsers** : detected browners in a network.
- **Printers** : configured printers in a network.
- **Soffid parameters** : you can specify a parameter to be applied only in a network.
- **Network discovery** : to discover the machines and systems in the configured networks.

Standard attributes

- **Name:** identifier name of the printer.
- **Description:** additional printer information.
- **Printing server:** where the printer is hosted.
- **Model:** printer model.
- **Restricted:** if checked, only users and groups of users assigned can be access to that, in another case any user could access to that printer.
- **Users:** assignment of printer queues to users.
- **Groups:** assignment of printer queues to groups

Actions

Printers table

"Query"	Allows you to query printers through different search systems, Quick , Basic and Advanced .
Add new	Allows you to create a new printer. To add a new printer it will be mandatory to fill in the required fields
Delete printer	Allows you to remove one or more printers by selecting one or more records and next clicking this button. To perform that action, Soffid will ask you for confirmation, you could confirm or cancel the operation.
Download CSV file	Allows you to download a csv file with the basic information of all printers.

Import	Allows you to upload a CSV file with the printer list to add or update printers to Soffid. First, you need to pick up a CSV file, that CSV has to contain a specific configuration. Then you need to check the content to be loaded, it is allowed to choose if you want or not to load a specific attribute. And finally, you need to select the mappings for each column of the CSV file to import the data correctly and to click the Import button.
View	Allows you to show and hide columns in the table. You can also set the order in which the columns will be displayed.

Printer detail

Add new	Allows you to create a new printer. To add a new printer it will be mandatory to fill in the required fields and apply changes.
Delete	Allows you to remove one printer. To perform that action, Soffid will ask you for confirmation, you could confirm or cancel the operation.
Undo	Allows you to quit without applying any changes.

Revision #12

Created 26 June 2025 13:28:48 by Sion Vives

Updated 22 September 2025 13:01:06 by Sion Vives