

Full PAM installation using Docker Compose

Introduction

This tutorial will describes **all the steps required to install and configure a basic PAM environment** for a local, demo or small production environment.

Prerequisites

- We have a **Linux** machine; Ubuntu 24 has been used for this tutorial.
- **Docker** and the **Docker Compose** plugin are already installed.
- The **database**, **Console** and **Syncserver** have already been installed.
- The Linux administrator user has **sudo privileges**.

Step 1: Prepare certificates

1.1 Some initial steps

This tutorial will use **self-signed certificates** generated for a lab environment.

If you have your **own certificates**, follow the steps depending on the file type.

For this tutorial, we will be using the following hostnames: **store.soffid4.local** and **launcher.soffid4.local**

Go to the current Soffid 4 **directory** where the docker-compose.yaml is located.

```
cd /home/user/lab/soffid4/ ---> (this is an example)
```

Add the hostnames in your **hosts** file.

```
sudo vim /etc/hosts ---> (use vim or your favourite editor)
```

```
127.0.0.1 store.soffid4.local  
127.0.0.1 launcher.soffid4.local
```

And now you will need **java**, confirm is you have it or not.

```
java -version
```

If you do not have it, for example **install java 17** (you can install another version).

```
sudo apt-get update  
sudo apt-get install openjdk-17-jdk  
java -version
```

1.2 Generate .key files

When you run the command, you will be prompted for a **password**. In this tutorial, we will always use the value **12345678**; please replace this with the password of your choice (minimum 8 characters)

```
sudo openssl genrsa -aes256 -out store.soffid4.local.key  
sudo openssl genrsa -aes256 -out launcher.soffid4.local.key
```

1.3 Generate .pem files

When you run the command, the prompt will ask for the **CN (Common Name)** attribute; use the values from our domains: **store.soffid4.local** or **launcher.soffid4.local**

```
sudo openssl req -x509 -days 1000 -new -key store.soffid4.local.key -out store.soffid4.local.pem  
sudo openssl req -x509 -days 1000 -new -key launcher.soffid4.local.key -out launcher.soffid4.local.pem
```

1.3 Generate .pfx files

```
sudo openssl pkcs12 -export -in store.soffid4.local.pem -inkey store.soffid4.local.key -out store.soffid4.local.pfx
sudo openssl pkcs12 -export -in launcher.soffid4.local.pem -inkey launcher.soffid4.local.key -out
launcher.soffid4.local.pfx
```

1.4 Generate .jks files

```
sudo keytool -v -importkeystore -srckeystore store.soffid4.local.pfx -srcstoretype PKCS12 -destkeystore
store.soffid4.local.jks -deststoretype JKS -destkeypass 12345678 -srcstorepass 12345678 -deststorepass
12345678
sudo keytool -v -importkeystore -srckeystore launcher.soffid4.local.pfx -srcstoretype PKCS12 -destkeystore
launcher.soffid4.local.jks -deststoretype JKS -destkeypass 12345678 -srcstorepass 12345678 -deststorepass
12345678
```

Step 2: Store configuration

2.1 Add the store in the yaml file

Edit your docker-compose.yaml.

```
sudo vim docker-compose.yaml
```

Add the store service in your docker-compose.yaml.

For this tutorial, **ports 8090** and **8091** have been opened.

```
services:
  store:
    image: soffid/pam-store:1.4.88
    environment:
      JAVA_KEYSTORE: /opt/soffid/tomee/certificates/store.soffid4.local.jks
      KEYSTORE_PASS: 12345678
    ports:
      - "8090:8080"
      - "8091:8443"
    networks:
      - network
    volumes:
      - store-trustedcerts:/opt/soffid/tomee/trustedcerts
```

- store-certificates:/opt/soffid/tomee/certificates
- store-data:/opt/soffid/tomee/data

volumes:

store-trustedcerts:

name: soffid4-pam-store-trustedcerts

store-certificates:

name: soffid4-pam-store-certificates

store-data:

name: soffid4-pam-store-data

Regenerate the docker containers.

```
sudo docker compose up -d
```

2.2 Create users

The **console** and the **launcher** will need **users** to **connect** to the **store**.

We have to **run a script** in the **store** container to **create the user**. This script has two parameters, the user name, and the role. The role options are "console" or "launcher".

When the user is created, its **password** is **generated** and displayed in the script's output; please **copy and save it** for use in the next steps.

Create the **user-console**.

```
docker compose exec store /opt/soffid/tomee/bin/add-user.sh user-console console
```

```
/bin/bash: warning: setlocale: LC_ALL: cannot change locale (en_US.UTF-8)
```

```
Password: cccccc/Qul9NFIqQnDU73gYccccVHThyew7Qt8Hqpf0rEzVq1Ft7azccccccc
```

Create the **user-launcher**.

```
docker compose exec store /opt/soffid/tomee/bin/add-user.sh user-launcher launcher
```

```
/bin/bash: warning: setlocale: LC_ALL: cannot change locale (en_US.UTF-8)
```

```
Password: asdadadasdads/Qul9NFIqQnDU73gYccccVHThyew7Qt8Hqpf0rEzVq1Ft7aadadadasd
```

2.3 Add the certificate

Copy the **jks certificate** into the container.

```
docker compose cp store soffid4.local.jks store:/opt/soffid/tomee/certificates
```

Restart the store.


```
docker compose restart store
```

2.4 Monitoring the store

If the store has started successfully, we will be able to access the store's **monitoring** page.

<https://store soffid4.local:8091/store/check>


You must use the **user-console** username to log in.



This is result.



Confirm the CN name (Not secure > Certificate details).



If something has gone wrong, you need to check the log.

```
sudo docker compose logs store
```

Step 3: Launcher configuration

3.1 Add the launcher in the yaml file

Edit your docker-compose.yaml.

```
sudo vim docker-compose.yaml
```

Add the launcher service in your docker-compose.yaml.

For this tutorial, **ports 8092** and **8093** have been opened.

Update the **STORE_PASSWORD** value for the one generated previously.

```
services:
  launcher:
    image: soffid/pam-launcher:1.4.88
    environment:
      JAVA_KEYSTORE: /opt/soffid/tomee/certificates/launcher.soffid4.local.jks
      KEYSTORE_PASS: 12345678
      STORE_SERVER: http://store:8080
      STORE_USER: user-launcher
      STORE_PASSWORD: asdadadasdads/QuI9NFIqQnDU73gYccccVHThyew7Qt8Hqpf0rEzVq1Ft7aadadadasd
    ports:
```

```
- "8092:8080"
```

```
- "8093:8443"
```

```
networks:
```

```
- network
```

```
volumes:
```

```
- launcher-trustedcerts:/opt/soffid/tomee/trustedcerts
```

```
- launcher-certificates:/opt/soffid/tomee/certificates
```

```
- launcher-data:/opt/soffid/tomee/launcher
```

```
- /var/run/docker.sock:/var/run/docker.sock
```

```
volumes:
```

```
launcher-trustedcerts:
```

```
name: soffid4-pam-launcher-trustedcerts
```

```
launcher-certificates:
```

```
name: soffid4-pam-launcher-certificates
```

```
launcher-data:
```

```
name: soffid4-pam-launcher-data
```

Regenerate the docker containers.

```
sudo docker compose up -d
```

3.2 Add the certificate

Copy the **jks certificate** into the container.

```
docker compose cp launcher.soffid4.local.jks launcher:/opt/soffid/tomee/certificates
```

Restart the launcher.


```
docker compose restart launcher
```

3.3 Monitoring the launcher


If the launcher has started successfully, we will be able to access the store's **monitoring** page.

<https://launcher.soffid4.local:8093/launch/status>

This is result.



Confirm the CN name (Not secure > Certificate details).



If something has gone wrong, you need to check the log.

```
sudo docker compose logs launcher
```

Step 4: Register certificates

4.1 In the Console

Add the PAM hostnames in the console service.

Check the **IP** of the **docker environment**, in this tutorial 192.168.122.1.

```
sudo vim docker-compose.yaml

extra_hosts:
  - store.woffid4.local:192.168.122.1
  - launcher.woffid4.local:192.168.122.1

docker compose up -d
```

Created the PAM certificates for the Console.

```
docker compose exec -it console bash
cd /opt/soffid/iam-console-4/trustedcerts
openssl s_client -connect store.soffid4.local:8091 < /dev/null | sed -ne '/-BEGIN CERTIFICATE-/,/-END
CERTIFICATE-/p' > store.soffid4.local.crt
openssl s_client -connect launcher.soffid4.local:8093 < /dev/null | sed -ne '/-BEGIN CERTIFICATE-/,/-END
CERTIFICATE-/p' > launcher.soffid4.local.crt
exit
docker compose restart console
```

4.2 Add a store certificate to the sync server

Add the PAM hostnames in the syncserver service.

```
sudo vim docker-compose.yaml

extra_hosts:
  - store.soffid4.local:192.168.122.1

docker compose up -d
```

Add a store certificate to the sync server

```
docker compose exec -it syncserver bash
cd /opt/soffid/iam-sync/conf
openssl s_client -connect store.soffid4.local:8091 < /dev/null | sed -ne '/-BEGIN CERTIFICATE-/,/-END
CERTIFICATE-/p' > store.soffid4.local.crt
keytool -import -file store.soffid4.local.crt -keystore cacerts -alias store.soffid4.local
password: changeit
exit
docker compose restart syncserver
```

4.3 Add the store/syncserver certificate to the launcher

Add hostnames in the launcher service.

```
sudo vim docker-compose.yaml

extra_hosts:
  - store.soffid4.local:192.168.122.1
```

```
docker compose up -d
```

Add the store/syncserver certificate to the launcher.

```
docker compose exec -it launcher bash
cd /opt/soffid/tomee/trustedcerts
openssl s_client -connect store.soffid4.local:8091 < /dev/null | sed -ne '/-BEGIN CERTIFICATE-/,/-END
CERTIFICATE-/p' > store.soffid4.local.crt
openssl s_client -connect sync-server-version4.network:1768 < /dev/null | sed -ne '/-BEGIN CERTIFICATE-/,/-END
CERTIFICATE-/p' > sync-server-version4.network.crt
exit
docker compose restart launcher
```

Step 5: Session types

5.1 Introduction

When starting a user session through the launcher, it requires images for each **session type**; you must **load** the **latest** docker **image** so that the launcher can start the session.

5.2 load images

Download only the session types that you need.

```
sudo docker pull soffid/soffid-pasr-ssh:latest
sudo docker pull soffid/soffid-pasr-rdp:latest
sudo docker pull soffid/soffid-pasr-http:latest
sudo docker pull soffid/soffid-pasr-https:latest
sudo docker pull soffid/soffid-pasr-jdbc:latest
sudo docker pull soffid/soffid-pasr-tn5250:latest
sudo docker pull soffid/soffid-pasr-kube:latest
sudo docker pull soffid/soffid-pasr-google-chrome:latest
sudo docker pull soffid/soffid-pasr-vnc:latest
sudo docker pull soffid/soffid-pasr-iaccess:latest
sudo docker pull soffid/soffid-pasr-sap:latest
sudo docker pull soffid/soffid-pasr-gke:latest
```

5.3 Save web sessions

To **save a web sessions** you will need to add some parameters to the launcher **system.properties**.

If it already exists, do nothing.

```
docker compose exec -it launcher bash
cd /opt/soffid/tomee/conf/
apt-get update
apt-get install vim
vim system.properties


SOFFID_PAM_PARAMS_http=--shm-size=1024m --privileged -eVNCSERVER=yes
SOFFID_PAM_PARAMS_https=--shm-size=1024m --privileged -eVNCSERVER=yes

exit
docker compose restart launcher
```

Step 6: Configure PAM in Console

6.1 Introduction

We can now go to the **Configure PAM session servers** page.



The screenshot shows the Soffid console interface. The left sidebar contains a menu with items: ISS, IGA, AM, PAM, and IRC. The main content area is titled 'Security settings' and contains several configuration options: Authorizations, Authentication, Password policies, Configure PAM session servers (highlighted with a red box), PAM policies, and PAM rules. The 'Configure PAM session servers' option is described as 'Add or remove PAM stores or launchers'.

6.2 Create the PAM group

Create a new group and you register the **store** with its **user** and **password**, along with the **launcher**.

If everything goes well, it will let you to save the changes!

The screenshot shows the Soffid web interface. On the left is a navigation menu with items: ISS, IGA, AM, PAM, and IRC. The main content area shows the breadcrumb path: Main Menu > Configuration > Security settings > Configure PAM session servers. The title of the page is 'Soffid4 PAM local'. Below the title are buttons for 'Expand all', 'Collapse all', and a refresh icon. A section titled 'Jump server group' contains a table with the following fields:

Group name *	Description *
Soffid4 PAM local	Soffid4 PAM local
User name *	Password *
user-console
URL *	Jump servers *
https://store.soffid4.local:8091	https://launcher.soffid4.local:8093
	Jump servers

At the bottom right of the configuration area are buttons for 'Undo' and 'Apply changes'.

Step 7: Open a web session

7.1 Password vault

Go to **Password vault** page.

soffid
Identity made simple

Advanced

- ISS
- IGA My OTP devices
- Resources >
- AM Tools >
- PAM Configuration >
- IRC Monitoring and reporting >

Search in Soffid...

Main Menu > Resources > Password vault

Add new

Name	Description
> Personal accounts	Accounts that won't be shared
> Password vault accounts	Password vault accounts

7.2 Create an account

Create a new folder "Password vault accounts" with the button "Add new".

Now, on the "Password vault accounts", click the three points icon and "Create new account".

Name	Description
> Personal accounts	Accounts that won't be shared
> Password vault accounts	Password vault accounts

- + Create new folder
- + Create new account

Add these values and click the dick button.



Expand all Collapse all 08

▼ **Common attributes :**

System * :

Name * :

Login name :

Description :

Type * :

Status :

Credential type :

Password policy * :

▼ **Owners :**

Owner users :

> **Managers :**

> **Password synchronization :**

▼ **Launch properties :**

Login url :

Launch type :

Jump server group :

> **SSO attributes :**

> **SSO Users :**

> **Password vault :**

> **Audit information :**

 Undo

Save a dummy password.

 **Soffid.com**
44


 **Launch**  **View password**  

Set account password

Generated password

Set password

Password



Cancel **OK**

7.3 Launch

Click the Launch button to confirm that the launcher can open the session type correctly.

 **Soffid.com**
44

 **Launch**  **View password**  

 This session is being recorded      

Tired of identity management headaches? 75%  



Don't get left behind

Identity management technology certifications

Wherever you go,
Soffid has you
covered!



Now you have the PAM environment ready to continu

Revision #11

Created 19 May 2026 06:11:29 by Sion Vives

Updated 22 May 2026 16:27:05 by Sion Vives